


# Pololu AVR C/C++ Library User's Guide



1. Introduction . . . . .	2
2. Prerequisites . . . . .	4
3. Downloading and extracting the files . . . . .	5
4. Compiling the Pololu AVR Library (Optional) . . . . .	6
5. Installation of the Pololu AVR Library . . . . .	7
6. Example programs . . . . .	9
6.a. Example program – AVR Studio . . . . .	9
6.b. Example program – Linux . . . . .	11
6.c. Orangutan Analog Input Functions . . . . .	12
6.d. Orangutan Buzzer Control Functions . . . . .	15
6.e. Orangutan Digital I/O Functions . . . . .	20
6.f. Orangutan LCD Control Functions . . . . .	22
6.g. Orangutan LED Control Functions . . . . .	25
6.h. Orangutan Motor Control Functions . . . . .	26
6.i. Orangutan Pushbutton Interface Functions . . . . .	27
6.j. Orangutan Serial Port Communication Functions . . . . .	28
6.k. Orangutan Servo Control Functions . . . . .	31
6.l. Orangutan SVP Functions . . . . .	36
6.m. Pololu QTR Sensor Functions . . . . .	38
6.n. Pololu Wheel Encoder functions . . . . .	41
7. Using the Pololu AVR Library for your own projects . . . . .	43
8. Additional resources . . . . .	45

# 1. Introduction

This document is a guide to using the Pololu AVR C/C++ library, including installation instructions, tutorials, and example programs. The Pololu AVR Library makes it easy for you to get started with the following Pololu products:



**Pololu 3pi robot:** a mega168/328-based robot controller. The 3pi robot essentially contains an SV-328 and a 5-sensor version of the QTR-8RC, both of which are in the list below.



**Pololu Orangutan SVP-324:** based on the mega324, the SVP-324 robot controller is a super-sized version of the SV-328, with a built-in AVR ISP programmer, more I/O lines, and more regulated power.



**Pololu Orangutan SVP-1284:** based on the mega1284, the SVP-1284 robot controller is a super-sized version of the SV-328, with a built-in AVR ISP programmer, more I/O lines, more regulated power, and more memory.



**Pololu Orangutan SV-328:** a full-featured, mega328-based robot controller that includes an LCD display. The SV-328 runs on an input voltage of 6-13.5V, giving you a wide range of robot power supply options, and can supply up to 3 A on its regulated 5 V bus. This library also supports the original **Orangutan SV-168**, which was replaced by the SV-328.



**Pololu Orangutan LV-168:** a full-featured, mega168-based robot controller that includes an LCD display. The LV-168 runs on an input voltage of 2-5V, allowing two or three batteries to power a robot.



**Pololu Baby Orangutan B-48:** a compact, complete robot controller based on the mega48. The B-48 packs a voltage regulator, processor, and a two-channel motor-driver into a 24-pin DIP format.



**Pololu Baby Orangutan B-328:** a mega328 version of the above. The mega328 offers more memory for your programs (32 KB flash, 2 KB RAM). This library also supports the **Baby Orangutan B-168**, which was replaced by the Baby B-328.



**Pololu QTR-1A and QTR-8A reflectance sensors (analog):** an analog sensor containing IR/phototransistor pairs that allows a robot to detect the difference between shades of color. The QTR sensors can be used for following lines on the floor, for obstacle or drop-off (stairway) detection, and for various other applications.



**Pololu QTR-1RC and QTR-8RC reflectance sensors (RC):** a version of the above that is read using digital inputs; this is compatible with the Parallax QTI sensors.



**Encoder for Pololu Wheel 42x19 mm:** a wheel encoder solution that allows a robot to measure how far it has traveled.

Note that the library is designed for Atmel's mega168 and mega48-based boards like the Orangutans: to use it with the QTR sensors, your controller must be either an Orangutan or another board built with one of these processors.

This document covers the C/C++ version of the library, but it may also be used with **Arduino** [<http://www.arduino.cc>]: a popular, beginner-friendly programming environment for the mega168, using simplified C++ code. See our **guide to using Arduino with Orangutan controllers** [<http://www.pololu.com/docs/0J17>] for more information.

For detailed information about all of the functions available in the library, see the **command reference** [<http://www.pololu.com/docs/0J18>].

## 2. Prerequisites

The free avr-gcc compiler, avr-libc, and other associated tools must be installed before the Pololu AVR library.

### Installing the AVR development tools for Windows

For Windows users, these tools are made available as the **WinAVR distribution** [<http://winavr.sourceforge.net/>]. We also recommend the **AVR Studio development environment** [<http://www.atmel.com/avrstudio/>], which may be downloaded free of charge from Atmel. To load your compiled code onto the Pololu Orangutan or 3pi, we recommend the **Pololu USB AVR Programmer** [<http://www.pololu.com/catalog/product/1300>], but any AVR ISP programmer will work. If you will be using a Pololu programmer, follow the **installation instructions** [<http://www.pololu.com/docs/0J36>] to install it on your computer, before continuing with these instructions.

Windows Vista: WinAVR might not work without additional help from this **WinAVR and Windows Vista Guide** [<http://www.madwizard.org/electronics/articles/winavr vista>]

### Installing the AVR development tools for Linux

Linux users should install all AVR-related packages available in their distribution's package manager. In particular, under Ubuntu you will need to install the following packages:

- avr-libc
- gcc-avr
- avra
- binutils-avr
- avrdude (for use with the Pololu Orangutan Programmer)

**Note:** The new ATmega328p processor is not supported by some versions of Linux. Please see our reference: **Developing for the ATmega328P under Linux** [<http://www.pololu.com/docs/0J31>].

### 3. Downloading and extracting the files

To begin the installation process for the Pololu AVR C/C++ Library, you will need to download the zip file:

- **Pololu AVR Library** [[http://www.pololu.com/file/download/libpololu-avr-100129.zip?file\\_id=0J325](http://www.pololu.com/file/download/libpololu-avr-100129.zip?file_id=0J325)] (1275k zip) released 2010-1-29

Next, if you are using Windows: open the .zip file and click “Extract all” to extract the Pololu AVR Library files to a folder on your desktop.

If you are using Linux, run the command `unzip libpololu-avr-xxx.zip`, where xxx is replaced by the version of the library that you have downloaded.

A directory called “libpololu-avr” will be created.

#### Older versions of the library

These are available in case you have trouble with the most recent version.

- **libpololu-avr-091201.zip** [[http://www.pololu.com/file/download/libpololu-avr-091201.zip?file\\_id=0J281](http://www.pololu.com/file/download/libpololu-avr-091201.zip?file_id=0J281)] (1063k zip)
- **libpololu-avr-091106.zip** [[http://www.pololu.com/file/download/libpololu-avr-091106.zip?file\\_id=0J262](http://www.pololu.com/file/download/libpololu-avr-091106.zip?file_id=0J262)] (1064k zip)
- **libpololu-avr-090605.zip** [[http://www.pololu.com/file/download/libpololu-avr-090605.zip?file\\_id=0J200](http://www.pololu.com/file/download/libpololu-avr-090605.zip?file_id=0J200)] (721k zip)
- **libpololu-avr-090420.zip** [[http://www.pololu.com/file/download/libpololu-avr-090420.zip?file\\_id=0J192](http://www.pololu.com/file/download/libpololu-avr-090420.zip?file_id=0J192)] (719k zip)
- **libpololu-avr-090414.src.zip** [[http://www.pololu.com/file/download/libpololu-avr-090414.zip?file\\_id=0J191](http://www.pololu.com/file/download/libpololu-avr-090414.zip?file_id=0J191)] (877k zip)
- **libpololu-avr-081209.src.zip** [[http://www.pololu.com/file/download/libpololu-avr-081209.src.zip?file\\_id=0J145](http://www.pololu.com/file/download/libpololu-avr-081209.src.zip?file_id=0J145)] (295k zip)
- **libpololu-avr-081209.zip** [[http://www.pololu.com/file/download/libpololu-avr-081209.zip?file\\_id=0J144](http://www.pololu.com/file/download/libpololu-avr-081209.zip?file_id=0J144)] (254k zip)
- **libpololu-avr-081104.src.zip** [[http://www.pololu.com/file/download/libpololu-avr-081104.src.zip?file\\_id=0J140](http://www.pololu.com/file/download/libpololu-avr-081104.src.zip?file_id=0J140)] (292k zip)
- **libpololu-avr-081104.zip** [[http://www.pololu.com/file/download/libpololu-avr-081104.zip?file\\_id=0J139](http://www.pololu.com/file/download/libpololu-avr-081104.zip?file_id=0J139)] (251k zip)

## 4. Compiling the Pololu AVR Library (Optional)

This section is optional, for people who want to modify the library or get a better understanding of how it works. If you just want to install the library, proceed to **Section 5**.

Unpack the entire archive and open a command prompt within the libpololu-avr directory. If `avr-gcc` is correctly installed on your system, you will be able to type “make clean”, then “make” to compile the entire library. Pay attention to any errors that occur during the build process. If all goes well, this will generate three versions of the library, for the ATmega48, ATmega168, ATmega328P, ATmega324PA, and ATmega1284P. If you see errors, it is likely that `avr-gcc` was installed improperly or in a way that is incompatible with the Makefile.

```

Microsoft Windows [Version 6.0.6001]
Copyright (c) 2006 Microsoft Corporation. All rights reserved.

C:\Users\paul\Desktop\libpololu-avr>
C:\Users\paul\Desktop\libpololu-avr>make
avr-g++ -g -Wall -mcall-prologues -mmcu=atmega168 -DLIB_POLOLU -ffunction-sections -fcommon -O2 -c src/OrangutanMotors/OrangutanMotors.o -o src/OrangutanMotors/OrangutanMotors.o
avr-g++ -g -Wall -mcall-prologues -mmcu=atmega168 -DLIB_POLOLU -ffunction-sections -fcommon -O2 -c src/OrangutanBuzzers/OrangutanBuzzers.o -o src/OrangutanBuzzers/OrangutanBuzzers.o
avr-g++ -g -Wall -mcall-prologues -mmcu=atmega168 -DLIB_POLOLU -ffunction-sections -fcommon -O2 -c src/OrangutanPushButtons/OrangutanPushButtons.o -o src/OrangutanPushButtons/OrangutanPushButtons.o
avr-g++ -g -Wall -mcall-prologues -mmcu=atmega168 -DLIB_POLOLU -ffunction-sections -fcommon -O2 -c src/OrangutanLCD/OrangutanLCD.o -o src/OrangutanLCD/OrangutanLCD.o
avr-g++ -g -Wall -mcall-prologues -mmcu=atmega168 -DLIB_POLOLU -ffunction-sections -fcommon -O2 -c src/OrangutanLEDs/OrangutanLEDs.o -o src/OrangutanLEDs/OrangutanLEDs.o
avr-g++ -g -Wall -mcall-prologues -mmcu=atmega168 -DLIB_POLOLU -ffunction-sections -fcommon -O2 -c src/OrangutanAnalog/OrangutanAnalog.o -o src/OrangutanAnalog/OrangutanAnalog.o
avr-g++ -g -Wall -mcall-prologues -mmcu=atmega168 -DLIB_POLOLU -ffunction-sections -fcommon -O2 -c src/PololuQTRSensors/PololuQTRSensors.o -o src/PololuQTRSensors/PololuQTRSensors.o
avr-g++ -g -Wall -mcall-prologues -mmcu=atmega168 -DLIB_POLOLU -ffunction-sections -fcommon -O2 -c src/Pololu3Pi/Pololu3Pi.o -o src/Pololu3Pi/Pololu3Pi.o
avr-g++ -g -Wall -mcall-prologues -mmcu=atmega168 -DLIB_POLOLU -ffunction-sections -fcommon -O2 -c src/OrangutanResources/OrangutanResources.o -o src/OrangutanResources/OrangutanResources.o
avr-g++ -g -Wall -mcall-prologues -mmcu=atmega168 -DLIB_POLOLU -ffunction-sections -fcommon -O2 -c src/OrangutanTime/OrangutanTime.o -o src/OrangutanTime/OrangutanTime.o
avr-ar rs libpololu.a src/OrangutanMotors/OrangutanMotors.o src/OrangutanBuzzers/OrangutanBuzzers.o src/OrangutanPushButtons/OrangutanPushButtons.o src/OrangutanLCD/OrangutanLCD.o src/OrangutanLEDs/OrangutanLEDs.o src/OrangutanAnalog/OrangutanAnalog.o src/PololuQTRSensors/PololuQTRSensors.o src/Pololu3Pi/Pololu3Pi.o src/OrangutanResources/OrangutanResources.o src/OrangutanTime/OrangutanTime.o
avr-ari creating libpololu.a
C:\Users\paul\Desktop\libpololu-avr>
  
```

Compiling the Pololu AVR Library from the command prompt in Windows.

## 5. Installation of the Pololu AVR Library

### Automatic installation

The automatic installation installs all Pololu AVR Library files in the location of your avr-gcc installation. This is done by running `install.bat` or by opening a command prompt and typing “make install”.

Windows Vista: right click on `install.bat` and select “Run as administrator”.

If the automatic installation works, you can proceed to **Section 6** to try out some example programs.


### Manual installation (if necessary)

Determine the location of your avr-gcc files. In Windows, they will usually be in a folder such as: `C:\WinAVR-20080610\avr`. In Linux, the avr-gcc files are probably located in `/usr/avr`.

If you currently have an older version of the Pololu AVR Library, your first step should be to delete all of the old include files and the `libpololu.a` file or `libpololu_atmegaX.a` files that you installed previously.

Next, copy `libpololu_atmega48.a`, `libpololu_atmega168.a`, `libpololu_atmega328p.a`, `libpololu_atmega324p.a`, and `libpololu_atmega1284p.a` into the `lib` subdirectory of your **avr** directory (e.g. `C:\WinAVR-20080610\avr\lib`). Note that there is also a `lib` subdirectory directly below the main WinAVR directory; it will not work to put the `libpololu_atmegaX.a` files here. These three library files represent separate compilations for the four different AVR microcontrollers found on our Orangutans and 3pi robot. When you make your own projects, you will need to use the appropriate library for your particular microcontroller.

Finally, copy the entire `pololu` subfolder into the `include` subfolder. The Pololu include files should now be located in `avr\include\pololu`.



**The Pololu AVR Library header files, installed correctly.**

You are now ready to use the Pololu AVR library. The next section provides example programs that are already set up to use the library. For information on using the Pololu AVR library in your own programs (e.g. configuring AVR Studio projects to use the library), please see **Section 7**.




## 6. Example programs

### 6.a. Example program - AVR Studio


A very simple demo program for the Orangutan or 3pi is available in the folder `examples\atmegaXXX\simple-test`, where `atmegaXXX` is the model of the microcontroller on your board.

Double-click on the file `test.aps`, and the project should open automatically in AVR Studio, showing a C file that uses a few basic commands from the Pololu AVR Library:



AVR Studio showing the sample program.

To compile this program, select **Build > Build** or press **F7**. Look for warnings and errors (indicated by yellow and red dots) in the output displayed below. If the program compiles successfully, the message “Build succeeded with 0 Warnings...” will appear at the end of the output, and a file `test.hex` will have been created in the `simple-test\default` folder.



```
Build
Build started 15.7.2008 at 10:10:02
● avr-gcc.exe -mmcu=atmega168 -Wall -gdwarf-2 -std=gnu99 -Os -funsigned
● avr-gcc.exe -mmcu=atmega168 -Wl,-gc-sections -Wl,-Map=test.map test.o
● avr-objcopy -O ihex -R .eeprom test.elf test.hex
● avr-objcopy -j .eeprom --set-section-flags=.eeprom="alloc,load" --cha
avr-objdump -h -S test.elf > test.lss

AVR Memory Usage
-----
Device: atmega168

Program: 3190 bytes (19.5% Full)
(.text + .data + .bootloader)

Data: 40 bytes (3.9% Full)
(.data + .bss + .noinit)


Build succeeded with 0 Warnings...
```

**AVR Studio build window, compiling the example project.**

Connect your programmer to your computer and your Orangutan board or 3pi robot, and turn on the target's power. If you are using a Pololu programmer, its LEDs will give you feedback as to whether it has a good connection to the target (see the programmer's user's guide for more information).

Select **Tools > Program AVR > Connect** to connect to the programmer. If you are using a Pololu programmer, select "AVRISP" and "Auto". When you click the "Connect" button, the AVRISP programming window should appear.

You will use AVRISP to load test.hex into the flash memory of your AVR. To do this, click "..." in the Flash section and select file test.hex that was compiled earlier. Note that you have to first navigate to your project directory! Now click "Program" in the Flash section, and the test code should be loaded onto your Orangutan or 3pi.



**Programming the Orangutan from AVR Studio.**


If your controller was successfully programmed and you are using an Orangutan SV-xx8, Orangutan LV-168, or 3pi robot, you should hear a short tune, see the message “Hello!” on the LCD (if one is present and the contrast is set correctly), and the LEDs on the board should blink. If you are using a Baby Orangutan B, you will just see the red user LED blink.

In case you are having trouble performing the compilation, precompiled hex files for this example and all of the other examples included with the C/C++ library are available in `examples\processor\hex_files`. You can load these hex files onto your controller using AVR Studio as described above.

### **6.b. Example program - Linux**

A simple demo program is supplied in the directory `examples/atmegaXXX/simple-test/`, where `atmegaXXX` is the processor on your board.

Change to this directory and inspect the Makefile. Depending on your system, you may need to update the paths to the `avr-gcc` binaries and the device for your programmer. Then, you should be able to compile the example with `make`, which should generate the output like this as it compiles the source code:




```

~/libpololu-avr/test/simple-test$ make
/usr/bin/avr-gcc -g -Wall -mcalls-prologues -mmcu=atmega168 -Os -c -o test.o test.c
/usr/bin/avr-gcc -g -Wall -mcalls-prologues -mmcu=atmega168 -Os test.o -Wl,-gc-sections -lpololu -o test.obj
/usr/bin/avr-objcopy -R .eeprom -O ihex test.obj test.hex
rm test.obj
~/libpololu-avr/test/simple-test$

```

**Compiling the test program under Linux.**

If make completed successfully, connect your programmer to your computer and your Orangutan board or 3pi robot, and turn on the target's power. The green status LED close to the USB connector should be on, while the other two LEDs should be off, indicating that the programmer is ready. Type `make program` to load the program onto the Orangutan or 3pi. If your programmer is installed on a port other than `/dev/ttyUSB0` (for example if you are using the newer Pololu USB AVR Programmer) you will have to edit the Makefile and enter the correct port.



```

~/libpololu-avr/test/simple-test$ make program
/usr/bin/avrdude -p m168 -c avrisp2 -P /dev/ttyUSB0 -U flash:w:test.hex

avrdude: AVR device initialized and ready to accept instructions

Reading | ##### | 100% 0.02s

avrdude: Device signature = 0x1e9406
avrdude: NOTE: FLASH memory has been specified, an erase cycle will be performed
        To disable this feature, specify the -D option.
avrdude: erasing chip
avrdude: reading input file "test.hex"
avrdude: input file test.hex auto detected as Intel Hex
avrdude: writing flash (3196 bytes):

Writing | ##### | 100% 1.21s

avrdude: 3196 bytes of flash written
avrdude: verifying flash memory against test.hex:
avrdude: load data flash data from input file test.hex:
avrdude: input file test.hex auto detected as Intel Hex
avrdude: input file test.hex contains 3196 bytes
avrdude: reading on-chip flash data:

Reading | ##### | 100% 1.11s

avrdude: verifying ...
avrdude: 3196 bytes of flash verified

avrdude: safemode: Fuses OK

avrdude done. Thank you.

~/libpololu-avr/test/simple-test$

```

**Programming the Orangutan with avrdude under Linux.**

If your controller was successfully programmed and you are using an Orangutan SV/LV or a 3pi, you should hear a short tune, see the message "Hello!" on the LCD (if one is present and the contrast is set correctly), and the LEDs on the board should blink. If you are using a Baby Orangutan B, you will just see the red user LED blink.

## 6.c. Orangutan Analog Input Functions Overview

This section of the library provides a set of methods that can be used to read analog voltage inputs, as well as functions specifically designed to read the value of the trimmer potentiometer (on the **3pi Robot** [<http://www.pololu.com/catalog/product/975>], **Orangutan SV** [<http://www.pololu.com/catalog/product/1227>], **Orangutan LV-168** [<http://www.pololu.com/catalog/product/775>], **Orangutan SVP** [<http://www.pololu.com/catalog/product/1325>] and **Baby Orangutan**

**B** [<http://www.pololu.com/catalog/product/12201>], the value of the temperature sensor in tenths of a degree F or C (on the Orangutan LV-168 only), and the battery voltage (3pi robot, SV-xx8, or SVP).

C++ users: See **Section 5.a of Programming Orangutans and the 3pi Robot from the Arduino Environment** [<http://www.pololu.com/docs/0J17>] for examples of this class in the Arduino environment, which is almost identical to C++.

Complete documentation of the functions can be found in **Section 2 of the Pololu AVR Library Command Reference** [<http://www.pololu.com/docs/0J18>].

## Usage Examples

This library comes with two examples in `libpololu-avr/examples`. The Orangutan Motors examples also make limited use of this section.

### 1. analog1

Demonstrates how you can use the methods in this library to read the analog voltage of the trimmer potentiometer in the background while the rest of your code executes. If the ADC is free, the program starts a conversion on the **TRIMPOT** analog input (channel 7 on all devices except the SVP), and then it proceeds to execute the rest of the code in `loop()` while the ADC hardware works. Polling of the `analog_is_converting()` method allows the program to determine when the conversion is complete and to update its notion of the trimpot value accordingly. Feedback is given via the red user LED, whose brightness is made to scale with the trimpot position.

On the Orangutan SVP, this example code will work, but it is not the recommended way of reading the trimpot. The trimpot reading and averaging is done on the auxiliary processor, so a simple `avg=analog_read(TRIMPOT);` is sufficient to get the value of the trimpot and will not burden the CPU significantly. You can, however, change the channel number in the code below from **TRIMPOT** to a channel number from 0 to 7 in order to measure one of the eight analog ports on the AVR.

```
#include <pololu/orangutan.h>

/*
 * analog1: for the Orangutan LV/SV-xx8 or Baby Orangutan B
 *
 * This example uses the OrangutanAnalog functions to read the voltage
 * output of the trimpot in the background while the rest of the main
 * loop executes. The LED is flashed so that its brightness appears
 * proportional to the trimpot position. This example will work on
 * both the Orangutan LV/SV-xx8 and Baby Orangutan B.
 *
 * http://www.pololu.com/docs/0J20
 * http://www.pololu.com
 * http://forum.pololu.com
 */

unsigned int sum;
unsigned int avg;
unsigned char samples;

int main()
{
    set_analog_mode(MODE_8_BIT);    // 8-bit analog-to-digital conversions
    sum = 0;
    samples = 0;
    avg = 0;
    start_analog_conversion(TRIMPOT); // start initial conversion

    while(1)
    {
        if (!analog_is_converting())    // if conversion is done...
```

```

{
    sum += analog_conversion_result(); // get result
    start_analog_conversion(TRIMPOT); // start next conversion
    if (++samples == 20) // if 20 samples have been taken...
    {
        avg = sum / 20; // compute 20-sample average of ADC result
        samples = 0;
        sum = 0;
    }
}

// when avg 0, the red LED is almost totally off.
// when avg 255, the red LED is almost totally on.
// brightness should scale approximately linearly in between.
red_led(0); // red LED off
delay_us(256 - avg);
red_led(1); // red LED on
delay_us(avg+1);
}
}

```

## 2. analog2

Intended for use on the Orangutan LV-168. Note that it will run on the 3pi robot and Orangutan SV-xx8, but the displayed temperature will be incorrect as the analog input connected to the temperature sensor on the Orangutan LV-168 is connected to 2/3rds of the battery voltage on the 3pi and to 1/3rd of the battery voltage on the Orangutan SV-xx8. It displays on the LCD the trimmer potentiometer output in millivolts and the temperature sensor output in degrees Fahrenheit. If you hold a finger on the underside of the Orangutan LV-168's PCB near the center of the board, you should see the temperature reading slowly start to rise. Be careful not to zap the board with electrostatic discharge if you try this!

```

#include <pololu/orangutan.h>

/*
 * analog2: for the Orangutan LV/SV-xx8
 *
 * This example uses the OrangutanAnalog functions to read the voltage
 * output of the trimpot (in millivolts) and to read the Orangutan
 * LV-168's temperature sensor in degrees Fahrenheit. These values are
 * printed to the LCD 10 times per second. This example is intended
 * for use with the Orangutan LV/SV-xx8 only.
 *
 * You should see the trimpot voltage change as you turn it, and you can
 * get the temperature reading to slowly increase by holding a finger on the
 * underside of the Orangutan LV/SV-xx8's PCB near the center of the board.
 * Be careful not to zap the board with electrostatic discharge if you
 * try this!
 *
 * http://www.pololu.com/docs/0J20
 * http://www.pololu.com
 * http://forum.pololu.com
 */

int main()
{
    set_analog_mode(MODE_10_BIT); // 10-bit analog-to-digital conversions

    while(1) // run over and over again
    {
        lcd_goto_xy(0,0); // LCD cursor to home position (upper-left)
        print_long(to_millivolts(read_trimpot())); // trimpot output in mV
        print(" mV "); // added spaces are to overwrite left over chars

        lcd_goto_xy(0, 1); // LCD cursor to start of the second line

        unsigned int temp = read_temperature_f(); // get temp in tenths of a degree F
        print_long(temp/10); // get the whole number of degrees
        print_character('.'); // print the decimal point
        print_long(temp - (temp/10)*10); // print the tenths digit
        print_character(223); // print a degree symbol
        print("F "); // added spaces are to overwrite left over chars
    }
}

```

```

    delay_ms(100);           // wait for 100 ms (otherwise LCD flickers too much)
  }
}

```

## 6.d. Orangutan Buzzer Control Functions

### Overview

These functions allow you to easily control the buzzer on the **3pi robot** [<http://www.pololu.com/catalog/product/975>], **Orangutan SV** [<http://www.pololu.com/catalog/product/1227>], **Orangutan SVP** [<http://www.pololu.com/catalog/product/1325>] and **Orangutan LV-168** [<http://www.pololu.com/catalog/product/775>]. You have the option of playing either a note or a frequency for a specified duration at a specified volume, or you can use the **play()** method to play an entire melody in the background. Buzzer control is achieved using one of the Timer 1 PWM outputs, and duration timing is performed using a Timer 1 overflow interrupt.

**Note:** The OrangutanServos and OrangutanBuzzer libraries both use Timer 1, so they **will conflict with each other and any other code that relies on or reconfigures Timer 1**.

This library is incompatible with some older releases of WinAVR. If you experience any problems when using this library, make sure that your copy of the compiler is up-to-date. We know that it works with WinAVR 20080610.

The benefit to this approach is that you can play notes on the buzzer while leaving the CPU mostly free to execute the rest of your code. This means you can have a melody playing in the background while your Orangutan does its main task. You can poll the **isPlaying()** method to determine when the buzzer is finished playing.

C++ users: See **Section 5.b of Programming Orangutans and the 3pi Robot from the Arduino Environment** [<http://www.pololu.com/docs/0J17>] for examples of this class in the Arduino environment, which is almost identical to C++.

Complete documentation of the functions can be found in **Section 3 of the Pololu AVR Library Command Reference** [<http://www.pololu.com/docs/0J18>].

## Usage Examples

This library comes with three examples in `libpololu-avr/examples`.

### 1. buzzer1

Demonstrates one way to use this library's **play\_note()** method to play a simple melody stored in RAM. It should immediately start playing the melody, and you can use the top user pushbutton to stop and replay the melody. The example is structured so that you can add your own code to the main loop and the melody will still play normally in the background, assuming your code executes quickly enough to avoid inserting delays between the notes. You can use this same technique to play melodies that have been stored in EEPROM (the mega168 has enough room in EEPROM to store 170 notes; the mega328 has enough room in EEPROM to store 340 notes).

```

#include <pololu/orangutan.h>
/*

```

```

* buzzer1:
*
* This example uses the OrangutanBuzzer library to play a series of notes
* on the Orangutan's/3pi's buzzer. It also uses the OrangutanLCD library
* to display the notes its playing, and it uses the OrangutanPushbuttons
* library to allow the user to stop/reset the melody with the top
* pushbutton.
*
* http://www.pololu.com/docs/0J20
* http://www.pololu.com
* http://forum.pololu.com
*/

#define MELODY_LENGTH 95

// These arrays take up a total of 285 bytes of RAM (out of a 1k limit)
unsigned char note[MELODY_LENGTH] =
{
    E(5), SILENT_NOTE, E(5), SILENT_NOTE, E(5), SILENT_NOTE, C(5), E(5),
    G(5), SILENT_NOTE, G(4), SILENT_NOTE,

    C(5), G(4), SILENT_NOTE, E(4), A(4), B(4), B_FLAT(4), A(4), G(4),
    E(5), G(5), A(5), F(5), G(5), SILENT_NOTE, E(5), C(5), D(5), B(4),

    C(5), G(4), SILENT_NOTE, E(4), A(4), B(4), B_FLAT(4), A(4), G(4),
    E(5), G(5), A(5), F(5), G(5), SILENT_NOTE, E(5), C(5), D(5), B(4),

    SILENT_NOTE, G(5), F_SHARP(5), F(5), D_SHARP(5), E(5), SILENT_NOTE,
    G_SHARP(4), A(4), C(5), SILENT_NOTE, A(4), C(5), D(5),

    SILENT_NOTE, G(5), F_SHARP(5), F(5), D_SHARP(5), E(5), SILENT_NOTE,
    C(6), SILENT_NOTE, C(6), SILENT_NOTE, C(6),

    SILENT_NOTE, G(5), F_SHARP(5), F(5), D_SHARP(5), E(5), SILENT_NOTE,
    G_SHARP(4), A(4), C(5), SILENT_NOTE, A(4), C(5), D(5),

    SILENT_NOTE, E_FLAT(5), SILENT_NOTE, D(5), C(5)
};

unsigned int duration[MELODY_LENGTH] =
{
    100, 25, 125, 125, 125, 125, 125, 250, 250, 250, 250, 250,

    375, 125, 250, 375, 250, 250, 125, 250, 167, 167, 167, 250, 125, 125,
    125, 250, 125, 125, 375,

    375, 125, 250, 375, 250, 250, 125, 250, 167, 167, 167, 250, 125, 125,
    125, 250, 125, 125, 375,

    250, 125, 125, 125, 250, 125, 125, 125, 125, 125, 125, 125, 125, 125,
    250, 125, 125, 125, 250, 125, 125, 200, 50, 100, 25, 500,

    250, 125, 125, 125, 250, 125, 125, 125, 125, 125, 125, 125, 125, 125,
    250, 250, 125, 375, 500
};

unsigned char currentIdx;

int main() // run once, when the sketch starts
{
    currentIdx = 0;
    print("Music!");

    while(1) // run over and over again
    {
        // if we haven't finished playing the song and
        // the buzzer is ready for the next note, play the next note
        if (currentIdx < MELODY_LENGTH && !is_playing())
        {
            // play note at max volume
            play_note(note[currentIdx], duration[currentIdx], 15);

            // optional LCD feedback (for fun)
            lcd_goto_xy(0, 1); // go to start of the second LCD line
            if(note[currentIdx] != 255) // display blank for rests

```



```

    print_long(note[currentIdx]); // print integer value of the current note
    print("-");                  // overwrite any left over characters
    currentIdx++;
}

// Insert some other useful code here...
// the melody will play normally while the rest of your code executes
// as long as it executes quickly enough to keep from inserting delays
// between the notes.

// For example, let the top user pushbutton function as a stop/reset melody button
if (button_is_pressed(TOP_BUTTON))
{
    stop_playing(); // silence the buzzer
    if (currentIdx < MELODY_LENGTH)
        currentIdx = MELODY_LENGTH; // terminate the melody
    else
        currentIdx = 0; // restart the melody
    wait_for_button_release(TOP_BUTTON); // wait here for the button to be released
}
}

return 0;
}

```

## 2. buzzer2

Demonstrates how you can use this library's **play()** function to start a melody playing. Once started, the melody will play all the way to the end with no further action required from your code, and the rest of your program will execute as normal while the melody plays in the background. The **play()** function is driven entirely by the Timer1 overflow interrupt. The top user pushbutton will play a fugue by Bach from program memory, the middle user pushbutton will quietly play the C major scale up and back down from RAM, and the bottom user pushbutton will stop any melody that is currently playing or play a single note if the buzzer is currently inactive.

```

#include <pololu/orangutan.h>

/*
 * buzzer2:
 *
 * This example uses the OrangutanBuzzer functions to play a series of notes
 * on the Orangutan's/3pi's buzzer. It uses the OrangutanPushbuttons
 * library to allow the user select which melody plays.
 *
 * This example demonstrates the use of the play() method,
 * which plays the specified melody entirely in the background, requiring
 * no further action from the user once the method is called. The CPU
 * is then free to execute other code while the melody plays.
 *
 * http://www.pololu.com/docs/0J20
 * http://www.pololu.com
 * http://forum.pololu.com
 */

#include <avr/pgmspace.h> // this lets us refer to data in program space (i.e. flash)
// store this fugue in program space using the PROGMEM macro.
// Later we will play it directly from program space, bypassing the need to load it
// all into RAM first.
const char fugue[] PROGMEM =
"! 05 L16 agafaea dac+adaea fa<aa<bac#a dac#adaea f"
"06 dcd<b-d<ad<g d<f+d<gd<ad<b- d<dd<ed<f+d<g d<f+d<gd<ad"
"L8 MS <b-d<b-d MLe-<ge-<g MSc<ac<a ML d<fd<f 05 MS b-gb-g"
"ML >c#e>c#e MS afaf ML gc#gc# MS fdfd ML e<b-e<b-"
"06 L16ragafaea dac#adaea fa<aa<bac#a dac#adaea faeadaa"
"<b-acadg<b-g egdgcg<b-g <ag<b-gcf<af dfcf<b-f<af"
"<gf<af<b-e<ge c#e<b-e<ae<ge <fe<ge<ad<fd"
"05 e>ee>ef>df>d b->c#b->c#a>df>d e>ee>ef>df>d"
"e>d>c#>db>d>c#b >c#a>egfe f 06 dc#dfdc#<b c#4";

void loop() // run over and over again
{
    // wait here for one of the three buttons to be pushed
    unsigned char button = wait_for_button(ALL_BUTTONS);
}

```

```

clear();
if (button TOP_BUTTON)
{
    play_from_program_space(fugue);

    print("Fugue!");
    lcd_goto_xy(0, 1);
    print("fTash ->");
}
if (button MIDDLE_BUTTON)
{
    play("! V8 cdefgab>cbagfedc");
    print("C Major");
    lcd_goto_xy(0, 1);
    print("RAM ->");
}
if (button == BOTTOM_BUTTON)
{
    if (is_playing())
    {
        stop_playing();
        print("stopped");
    }
    else
    {
        play_note(A(5), 200, 15);
        print("note A5");
    }
}
}

int main()                // run once, when the program starts
{
    print("Press a");
    lcd_goto_xy(0, 1);
    print("button..");

    while(1)
        loop();

    return 0;
}

```

### 3. buzzer3

Demonstrates the use of this library's `playMode()` and `playCheck()` methods. In this example, automatic play mode is used to allow the melody to keep playing while it blinks the red user LED. Then the mode is switched to play-check mode during a phase where we are trying to accurately measure time. There are three `#define` macros that allow you to run this example in different ways and observe the result. Please see the comments at the top of the sketch for more detailed information.

```

#include <pololu/orangutan.h>

/*
 * buzzer3:
 *
 * This example uses the OrangutanBuzzer functions to play a series of notes
 * on the Orangutan's/3pi's buzzer. It uses the OrangutanPushbuttons
 * functions to allow the user select which melody plays.
 *
 * This example demonstrates the use of the play_mode()
 * and play_check() methods, which allow you to select
 * whether the melody sequence initiated by play() is
 * played automatically in the background by the Timer1 interrupt, or if
 * the play is driven by the play_check() method in your main loop.
 *
 * Automatic play mode should be used if your code has a lot of delays
 * and is not time critical. In this example, automatic mode is used
 * to allow the melody to keep playing while we blink the red user LED.
 *
 * Play-check mode should be used during parts of your code that are

```

```

* time critical. In automatic mode, the Timer1 interrupt is very slow
* when it loads the next note, and this can delay the execution of your.
* Using play-check mode allows you to control when the next note is
* loaded so that it doesn't occur in the middle of some time-sensitive
* measurement. In our example we use play-check mode to keep the melody
* going while performing timing measurements using Timer2. After the
* measurements, the maximum time measured is displayed on the LCD.
*
* Immediately below are three #define statements that allow you to alter
* the way this program runs. You should have one of the three lines
* uncommented while commenting out the other two:
*
* If only WORKING_CORRECTLY is uncommented, the program should run in its
* ideal state, using automatic play mode during the LED-blinking phase
* and using play-check mode during the timing phase. The maximum recorded
* time should be 20, as expected.
*
* If only ALWAYS_AUTOMATIC is uncommented, the program will use automatic
* play mode during both the LED-blinking phase and the timing phase. Here
* you will see the effect this has on the time measurements (instead of 20,
* you should see a maximum reading of around 27 or 28).
*
* If only ALWAYS_CHECK is uncommented, the program will be in play-check
* mode during both the LED-blinking phase and the timing phase. Here you
* will see the effect that the LED-blinking delays have on play-check
* mode (the sequence will be very choppy while the LED is blinking, but
* sound normal during the timing phase). The maximum timing reading should
* be 20, as expected.
*
* http://www.pololu.com/docs/0J20
* http://www.pololu.com
* http://forum.pololu.com
*/

// *** UNCOMMENT ONE OF THE FOLLOWING PRECOMPILER DIRECTIVES ***
// (the remaining two should be commented out)
#define WORKING_CORRECTLY // this is the right way to use playMode()
// #define ALWAYS_AUTOMATIC // playMode() is always PLAY_AUTOMATIC (timing is inaccurate)
// #define ALWAYS_CHECK // playMode() is always PLAY_CHECK (delays interrupt the sequence)

#include <avr/pgmspace.h>
const char rhapsody[] PROGMEM = "06 T40 L16 d#<b<f#<d#<f#<bd#f#"
    "T80 c#<b-<f#<c#<f#<b-c#8"
    "T180 d#<b<f#<d#f#>bd#f#c#b-<f#c#f#>b-c#8 c>c#<c#>c#<b>c#<c#>c#c>c#<c#>c#<b>c#<c#>c#"
    "c>c#<c#>c#<b->c#<c#>c#c>c#<c#>c#<b->c#<c#>c#"
    "c>c#<c#>c#f>c#<c#>c#c>c#<c#>c#f>c#<c#>c#"
    "c>c#<c#>c#f#>c#<c#>c#c>c#<c#>c#f#>c#<c#>c#d#bb-bd#bf#d#c#b-ab-c#b-f#d#";

int main()
{
    TCCR2A = 0; // configure timer2 to run at 78 kHz
    TCCR2B = 0x06; // and overflow when TCNT2 = 256 (~3 ms)
    play_from_program_space(rhapsody);

    while(1)
    {
        // allow the sequence to keep playing automatically through the following delays
#ifdef ALWAYS_CHECK
        play_mode(PLAY_AUTOMATIC);
#else
        play_mode(PLAY_CHECK);
#endif
        lcd_goto_xy(0, 0);
        print("blink!");
        int i;
        for (i = 0; i < 8; i++)
        {
#ifdef ALWAYS_CHECK
            play_check();
#endif
            red_led(1);
            delay_ms(500);
            red_led(0);
            delay_ms(500);
        }

        lcd_goto_xy(0, 0);
    }
}

```

```

    print("timing");
    lcd_goto_xy(0, 1);
    print(" "); // clear bottom LCD line
    // turn off automatic playing so that our time-critical code won't be interrupted by
    // the buzzer's long timer1 interrupt. Otherwise, this interrupt could throw off our
    // timing measurements. Instead, we will now use playCheck() to keep the sequence
    // playing in a way that won't throw off our measurements.
#ifdef ALWAYS_AUTOMATIC
    play_mode(PLAY_CHECK);
#endif
    unsigned char maxTime = 0;
    for (i = 0; i < 8000; i++)
    {
        TCNT2 = 0;
        while (TCNT2 < 20) // time for ~250 us
        {
            if (TCNT2 > maxTime)
            {
                maxTime = TCNT2; // if the elapsed time is greater than the previous max, save it
            }
#ifdef ALWAYS_AUTOMATIC
            play_check(); // check if it's time to play the next note and play it if so
#endif
        }
        lcd_goto_xy(0, 1);
        print("max=");
        print_long((unsigned int)maxTime);
        print(" "); // overwrite any left over characters
    }

    return 0;
}

```

## 6.e. Orangutan Digital I/O Functions

### Overview

This section of the library provides commands for using the AVR's pins as generic digital inputs and outputs. Every pin on the AVR that has a name starting with P, followed by a letter and number (e.g. PC2) can be configured as a *digital input* or *digital output*. The program running on the AVR can change the configuration of these pins on the fly using the functions in this library.

Complete documentation of these functions can be found in **Section 4** of the **Pololu AVR Library Command Reference** [<http://www.pololu.com/docs/0J18>].

### Digital outputs

When a pin is configured as a digital output, the AVR is either driving it low (0 V) or high (5 V). This means that the pin has a strong electrical connection to either 0 V (GND) or 5 V (VCC). An output pin can be used to send data to a peripheral device or supply a small amount of power (for example, to light an LED).

### Digital inputs

When a pin is configured as a digital input, the AVR can read the voltage on the pin. The reading is always either low (0) or high (1). Basically, a low reading means that the voltage is close to 0 V, while a high reading means that the voltage is close to 5 V (see the DC characteristics section of your AVR's datasheet for details). Note that when we talk about absolute voltages in this document, we are assuming that the voltage of the ground (GND) line is defined to be 0 V.

Every I/O pin on the AVR comes with an internal 20–50 kilo-ohm *pull-up resistor* that can be enabled or disabled. A pull-up resistor is a resistor with a relatively high resistance that connects between a pin and the 5 V supply (VCC). If nothing is driving the pin strongly, then the pull-up resistor will pull the voltage on the pin up to 5 V. Pull-up resistors are useful for ensuring that your input pin reaches a well-known state when nothing is connected to it. If your input pin has nothing connected to it and the pull-up resistor is disabled, then it is called a *floating* pin. In

general, it is not recommended to take a digital reading on a floating pin, because the reading will be unpredictable.

An input pin can be used to read data from a sensor or other peripheral.

When the AVR powers up, all I/O pins are configured as inputs with their pull-up resistors disabled.

### Caveats

To use your digital I/O pins correctly and safely, there are several things you should be aware of:

- **Maximum voltage ratings:** Be sure to not expose your input pins to voltages outside their allowed range, which is -0.5 V – 5.5 V (assuming a VCC of 5 V). For example, do not connect any AVR pins directly to an RS-232 output, which varies between -12 V and 12 V. You can use a voltage divider circuit to overcome this limitation.
- **Drawing too much current from an output pin:** Be sure you do not attempt to draw too much current from your output pin; it may break. Basically, each output pin can supply up to 20 mA of current (see the DC characteristics section of your AVR's datasheet for details). This is enough to power typical LEDs, but is too small for many other devices. You can use a transistor to overcome this limitation.
- **Shorts:** Be sure that you do not connect a high output pin to a low output pin. This connection is called a *short* because it results in a low-resistance path from VCC to ground which will conduct large amounts of current until something breaks.
- **Alternative functions:** Many of the pins on the AVR have alternative functions. If these alternate functions are enabled, then the functions in this library may not work on those pins. For example, if you have enabled UART0, then you can not control the output value on PD1 using these functions because PD1 serves as the serial transmit line.

### Usage Example

This library comes with an example in `libpololu-avr/examples`.

#### 1. digital1

This example program takes a digital reading on PC1, and uses that reading to decide whether to drive pin PD1 (the red LED pin) low or high. You can test that the example is working by connecting a wire from PC1 to ground. When the connection is made the red LED should change state.

```
#include <pololu/orangutan.h>

/*
 * digital1: for the Orangutan controllers and 3pi robot
 *
 * This example uses the OrangutanDigital functions to read a digital
 * input and set a digital output. It takes a reading on pin PC1, and
 * provides feedback about the reading on pin PD1 (the red LED pin).
 * If you connect a wire between PC1 and ground, you should see the
 * red LED change state.
 *
 * http://www.pololu.com/docs/0J20
 * http://www.pololu.com
 * http://forum.pololu.com
 */

int main()
{
    // Make PC1 be an input with its internal pull-up resistor enabled.
    // It will read high when nothing is connected to it.
```

```

    set_digital_input(IO_C1, PULL_UP_ENABLED);
    while(1)
    {
        if(is_digital_input_high(IO_C1))    // Take digital reading of PC1.
        {
            set_digital_output(IO_D1, HIGH); // PC1 is high, so drive PD1 high.
        }
        else
        {
            set_digital_output(IO_D1, LOW);  // PC1 is low, so drive PD1 low.
        }
    }
}

```

## 6.f. Orangutan LCD Control Functions

### Overview

This section of the library gives you the ability to control the 8x2 character LCD on the **3pi Robot** [<http://www.pololu.com/catalog/product/975>], **Orangutan SV** [<http://www.pololu.com/catalog/product/1227>], **Orangutan SVP** [<http://www.pololu.com/catalog/product/1325>], and **Orangutan LV-168** [<http://www.pololu.com/catalog/product/775>]. It implements the standard 4-bit HD44780 protocol, and it uses the busy-wait-flag feature to avoid the unnecessarily long delays present in other 4-bit LCD control libraries. This comprehensive library is meant to offer as much LCD control as possible, so it most likely gives you more methods than you need. Make sure to use the linker option `-Wl,-gc-sections` when compiling your code, so that these extra functions will not be included in your hex file. See **Section 7** for more information.

This library is designed to gracefully handle alternate use of the four LCD data lines. It will change their data direction registers and output states only when needed for an LCD command, after which it will immediately restore the registers to their previous states. This allows the LCD data lines to additionally function as pushbutton inputs and an LED driver.

C++ users: See **Section 5.c of Programming Orangutans and the 3pi Robot from the Arduino Environment** [<http://www.pololu.com/docs/0J17>] for examples of this class in the Arduino environment, which is almost identical to C++.

Complete documentation of this library's methods can be found in **Section 5 of the Pololu AVR Library Command Reference** [<http://www.pololu.com/docs/0J18>].

## Usage Examples

This library comes with two examples in `libpololu-avr/examples`.

### 1. lcd1

Demonstrates shifting the contents of the display by moving the word "Hello" around the two lines of the LCD.

```

#include <pololu/orangutan.h>

/*
 * lcd1: for the Orangutan controllers and 3pi robot
 *
 * This example uses the OrangutanLCD library to display things on the LCD.
 *
 * http://www.pololu.com/docs/0J20
 * http://www.pololu.com
 * http://forum.pololu.com
 */

int main()
{

```

```


while(1)
{
    print("Hello");           // display "Hello" at (0, 0), a.k.a. upper-left
    delay_ms(200);
    lcd_scroll(LCD_RIGHT, 3, 200); // shift the display right every 200ms three times
    clear();                  // clear the LCD
    lcd_goto_xy(3, 1);        // go to the fourth character of the second LCD line
    print("Hello");           // display "Hello" at (3, 1), a.k.a. lower-right
    delay_ms(200);
    lcd_scroll(LCD_LEFT, 3, 200); // shift the display left every 200ms three times
    clear();                  // clear the LCD
}

return 0;
}

```

## 1. lcd2

Demonstrates creating and displaying custom characters on the LCD. The following picture shows an example of custom characters, using them to display a bar graph of sensor readings and a smiley face:



```

#include <pololu/orangutan.h>

// get random functions
#include <stdlib.h>

/*
 * lcd2: for the Orangutan controllers and 3pi robot
 *
 * This example uses the OrangutanLCD functions to display custom
 * characters on the LCD. Simply push a any user pushbutton to
 * display a new, randomly chosen, custom mood character.
 *
 * http://www.pololu.com/docs/0J20
 * http://www.pololu.com
 * http://forum.pololu.com
 */

// define some custom "mood" characters
#include <avr/pgmspace.h> // this lets us refer to data in program space (i.e. flash)
const char happy[] PROGMEM = {
    0b00000,           // the five bits that make up the top row of the 5x8 character
    0b01010,
    0b01010,
    0b01010,
    0b01010,
    0b00000,
    0b10001,
    0b01110,
    0b00000
};

const char sad[] PROGMEM = {
    0b00000,
    0b01010,
    0b01010,
    0b01010,
    0b01010,
    0b00000,
    0b01110,
    0b10001,

```

```

    0b000000
};

const char indifferent[] PROGMEM = {
    0b000000,
    0b01010,
    0b01010,
    0b01010,
    0b000000,
    0b000000,
    0b01110,
    0b000000
};

const char surprised[] PROGMEM = {
    0b000000,
    0b01010,
    0b01010,
    0b000000,
    0b01110,
    0b10001,
    0b10001,
    0b01110
};

const char mocking[] PROGMEM = {
    0b000000,
    0b01010,
    0b01010,
    0b01010,
    0b000000,
    0b11111,
    0b00101,
    0b00010
};

char prevMood = 5;

int main()
{
    lcd_load_custom_character(happy, 0);
    lcd_load_custom_character(sad, 1);
    lcd_load_custom_character(indifferent, 2);
    lcd_load_custom_character(surprised, 3);
    lcd_load_custom_character(mocking, 4);
    clear(); // this must be called before we can use the custom characters
    print("mood: ?");

    // initialize the random number generator based on how long they hold the button the first time
    wait_for_button_press(ALL_BUTTONS);
    long seed = 0;
    while(button_is_pressed(ALL_BUTTONS))
        seed++;
    srand(seed);

    while(1)
    {
        lcd_goto_xy(6, 0); // move cursor to the correct position

        char mood;
        do
        {
            mood = random()%5;
        } while (mood == prevMood); // ensure we get a new mood that differs from the previous
        prevMood = mood;

        print_character(mood); // print a random mood character
        wait_for_button(ALL_BUTTONS); // wait for any button to be pressed
    }

    return 0;
}

```



## 6.g. Orangutan LED Control Functions

### Overview

These functions allow you to easily control the user LED(s) on the **3pi Robot** [<http://www.pololu.com/catalog/product/975>], **Orangutan SV** [<http://www.pololu.com/catalog/product/1227>], **Orangutan SVP** [<http://www.pololu.com/catalog/product/1325>], **Orangutan LV-168** [<http://www.pololu.com/catalog/product/775>], and **Baby Orangutan B** [<http://www.pololu.com/catalog/product/1220>]. On the Orangutan SV-xx8 and LV-168, there are two user LEDs on the top side of the PCB with the red LED on the bottom left and the green LED on the top right. On the 3pi, there are two user LEDs on the bottom side of the PCB with the red LED on the right (when looking at the bottom) and the green LED on the left. Additional LEDs included with the 3pi may be soldered in on the top side (in parallel with the surface-mount LEDs on the underside) for easier viewing. The Orangutan SVP has two user LEDs: a red LED on the bottom right and a green LED on the top left. The Baby Orangutan has a single red LED and no green LED.

Note that the red LED is on the same pin as the UART0 serial transmitter (PD1), so if you are using UART0 for serial transmission then the red LED commands will not work, and you will see the red LED blink briefly whenever data is transmitted on UART0. Note that the green LED is on the same pin as an LCD control pin; the green LED will blink briefly whenever data is sent to the LCD, but the two functions will otherwise not interfere with each other.

C++ users: See **Section 5.d of Programming Orangutans and the 3pi Robot from the Arduino Environment** [<http://www.pololu.com/docs/0J17>] for examples of this class in the Arduino environment, which is almost identical to C++.

Complete documentation of these functions can be found in **Section 9 of the Pololu AVR Library Command Reference** [<http://www.pololu.com/docs/0J18>].

This library comes with an example program in `libpololu-avr/examples`.

### 1. led1

A simple example that blinks LEDs.

```
#include <pololu/orangutan.h>

/*
 * led1: for the 3pi robot, Orangutan LV 168, Orangutan SV-xx8, Orangutan SVP,
 *       or Baby Orangutan B
 *
 * This program uses the OrangutanLEDs functions to control the red and green
 * LEDs on the 3pi robot or Orangutan. It will also work to control the red
 * LED on the Baby Orangutan B (which lacks a second, green LED).
 *
 * http://www.pololu.com/docs/0J20
 * http://www.pololu.com
 * http://forum.pololu.com
 */

int main()
{
    while(1)
    {
        red_led(1);           // red LED on
        delay_ms(1000);       // waits for a second
        red_led(0);           // red LED off
        delay_ms(1000);       // waits for a second
        green_led(1);         // green LED on (will not work on the Baby Orangutan)
        delay_ms(500);        // waits for 0.5 seconds
        green_led(0);         // green LED off (will not work on the Baby Orangutan)
        delay_ms(500);        // waits for 0.5 seconds
    }
}
```

```

    }
    return 0;
}

```

## 6.h. Orangutan Motor Control Functions

### Overview

This set of functions gives you the ability to control the motor drivers on the **3pi Robot** [<http://www.pololu.com/catalog/product/975>], **Orangutan SV** [<http://www.pololu.com/catalog/product/1227>], **Orangutan SVP** [<http://www.pololu.com/catalog/product/1325>], **Orangutan LV-168** [<http://www.pololu.com/catalog/product/775>], and **Baby Orangutan B** [<http://www.pololu.com/catalog/product/1220>]. It accomplishes this by using the four hardware PWM outputs from timers Timer0 and Timer2, so **this library will conflict with any other libraries that rely on or reconfigure Timer0 or Timer2.**

C++ users: See **Section 5.e of Programming Orangutans and the 3pi Robot from the Arduino Environment** [<http://www.pololu.com/docs/0J17>] for examples of this class in the Arduino environment, which is almost identical to C++.

Complete documentation of these functions can be found in **Section 7 of the Pololu AVR Library Command Reference** [<http://www.pololu.com/docs/0J18>].

### Usage Examples

This library comes with two examples in `libpololu-avr/examples`.

#### 1. motors1

Demonstrates controlling the motors using the trimmer potentiometer and uses the red LED for feedback.

```

#include <pololu/orangutan.h>

/*
 * motors1: for the Orangutan LV-168, Orangutan SV-xx8, Orangutan SVP,
 *          and Baby Orangutan B
 *
 * This example uses the OrangutanMotors functions to drive
 * motors in response to the position of user trimmer potentiometer
 * and blinks the red user LED at a rate determined by the trimmer
 * potentiometer position. It uses the OrangutanAnalog library to measure
 * the trimpot position, and it uses the OrangutanLEDs library to provide
 * limited feedback with the red user LED.
 *
 * http://www.pololu.com/docs/0J20
 * http://www.pololu.com
 * http://forum.pololu.com
 */

unsigned long prevMillis = 0;

int main()
{
    while(1)
    {
        // note that the following line could also be accomplished with:
        // int pot = analogRead(7);
        int pot = read_trimpot(); // determine the trimpot position
        int motorSpeed = pot/2-256; // turn pot reading into number between -256 and 255
        if(motorSpeed == -256)
            motorSpeed = -255; // 256 is out of range
        set_motors(motorSpeed, motorSpeed);

        int ledDelay = motorSpeed;
        if(ledDelay < 0)
            ledDelay = -ledDelay; // make the delay a non-negative number
    }
}

```

```

    ledDelay = 256-ledDelay; // the delay should be short when the speed is high
    red_led(1);              // turn red LED on
    delay_ms(ledDelay);
    red_led(0);              // turn red LED off
    delay_ms(ledDelay);
}
}

```

## 2. motors2

Demonstrates controlling the motors using the trimmer potentiometer, but it uses the LCD for most of the feedback, so it will not fully work on the Baby Orangutan.

```

#include <pololu/orangutan.h>

/*
 * motors2: for the 3pi robot, Orangutan LV-168,
 *          Orangutan SVP, and Orangutan SV-xx8.
 *
 * This example uses the OrangutanMotors and OrangutanLCD libraries to drive
 * motors in response to the position of user trimmer potentiometer
 * and to display the potentiometer position and desired motor speed
 * on the LCD. It uses the OrangutanAnalog library to measure the
 * trimpot position, and it uses the OrangutanLEDs library to provide
 * limited feedback with the red and green user LEDs.
 *
 * http://www.pololu.com/docs/0J20
 * http://www.pololu.com
 * http://forum.pololu.com
 */

int main()                      // run over and over again
{
    while(1)
    {
        // note that the following line could also be accomplished with:
        // int pot = analogRead(7);
        int pot = read_trimpot(); // determine the trimpot position

        // avoid clearing the LCD to reduce flicker
        lcd_goto_xy(0, 0);
        print("pot=");
        print_long(pot);          // print the trim pot position (0 - 1023)
        print(" ");              // overwrite any left over digits

        int motorSpeed = (512 - pot) / 2;
        lcd_goto_xy(0, 1);
        print("spd=");
        print_long(motorSpeed);    // print the resulting motor speed (-255 - 255)
        print(" ");
        set_motors(motorSpeed, motorSpeed); // set speeds of motors 1 and 2

        // all LEDs off
        red_led(0);
        green_led(0);
        // turn green LED on when motors are spinning forward
        if (motorSpeed > 0)
            green_led(1);
        // turn red LED on when motors are spinning in reverse
        if (motorSpeed < 0)
            red_led(1);
        delay_ms(100);
    }
}

```

### 6.i. Orangutan Pushbutton Interface Functions

#### Overview

This library allows you to easily interface with the three user pushbuttons on the **3pi robot** [<http://www.pololu.com/catalog/product/975>], **Orangutan SV** [<http://www.pololu.com/catalog/>]

**product/1227], Orangutan SVP** [<http://www.pololu.com/catalog/product/1325>], and **Orangutan LV-168** [<http://www.pololu.com/catalog/product/775>] by either polling for the state of specific buttons or by waiting for press/release events on specifiable buttons. The first time any function in this section is called, the function will initialize all the button I/O pins to be inputs and enable their internal pull-up resistors. The **wait\_for\_button\_...()** methods in this library automatically take care of button debouncing.

C++ users: See **Section 5.f of Programming Orangutans from the Arduino Environment** [<http://www.pololu.com/docs/0J17>] for examples of this class in the Arduino environment, which is almost identical to C++.

Complete documentation of these functions can be found in **Section 8 of the Pololu AVR Library Command Reference** [<http://www.pololu.com/docs/0J18>].

This library comes with an example program in `libpololu-avr/examples`.

## 1. pushbuttons1

Demonstrates interfacing with the user pushbuttons. It will wait for you to push either the top button or the bottom button, at which point it will display on the LCD which button was pressed. It will also detect when that button is subsequently released and display that to the LCD.

```
#include <pololu/orangutan.h>

/*
 * OrangutanPushbuttonExample: for the Orangutan LV-168,
 *   Orangutan SV-xx8, Orangutan SVP, and 3pi robot
 *
 * This example uses the OrangutanPushbuttons library to detect user
 * input from the pushbuttons, and it uses the OrangutanLCD library to
 * display feedback on the LCD.
 *
 * http://www.pololu.com/docs/0J20
 * http://www.pololu.com
 * http://forum.pololu.com
 */

int main()
{
    while(1)
    {
        clear();
        print("Waiting");

        // wait for either the top or bottom buttons to be pressed
        // store the value of the pressed button in the variable 'button'
        unsigned char button = wait_for_button_press(TOP_BUTTON | BOTTOM_BUTTON);
        clear();
        if (button == TOP_BUTTON)    // display the button that was pressed
            print("top down");
        else
            print("bot down");
        wait_for_button_release(button); // wait for that button to be released
        clear();
        print("released");           // display that the button was released
        delay_ms(1000);
    }
}
```

## 6.j. Orangutan Serial Port Communication Functions

### Overview

This section of the library provides routines for accessing the serial port (USART) on the **3pi robot** [<http://www.pololu.com/catalog/product/975>], **Orangutan SV** [<http://www.pololu.com/catalog/product/1227>], **Orangutan SVP** [<http://www.pololu.com/catalog/product/1325>], **Orangutan**

**LV-168** [<http://www.pololu.com/catalog/product/7751>], and **Baby Orangutan B** [<http://www.pololu.com/catalog/product/1220>].

The serial port routines normally use the **USART\_UDRE\_vect**, **USART\_RX\_vect**, **USART0\_UDRE\_vect**, **USART0\_RX\_vect**, **USART1\_UDRE\_vect**, and **USART1\_RX\_vect** interrupts, so they will conflict with any code that also uses these interrupts.

On the **3pi robot**, **Orangutan SV**, **\*Orangutan LV-168**, and **\*Baby Orangutan B**, using these functions will cause the red user LED functions to stop working, because the red LED is on the same pin as the UART transmitter (PD1/TXD). When the AVR is not transmitting bytes on TXD, the red LED will be on. When the AVR is transmitting bytes on TXD, the red LED will flicker.

On the **Orangutan SVP**, using these functions to control **UART0** will cause the red user LED functions to stop working, because the red LED is on the same pin as the **UART0** transmitter (PD1/TXD0). When the AVR is not transmitting bytes on TXD0, the red LED will be off. When the AVR is transmitting bytes on TXD0, the red LED will flicker. However, the AVR on the Orangutan SVP has two UARTs, so if you want to use the red LED and you only need one UART then you can use **UART1** instead of **UART0**.

Complete documentation of this library's methods can be found in **Section 9** of the **Pololu AVR Library Command Reference** [<http://www.pololu.com/docs/0J18>].

## Usage Examples

Example code for making the 3pi Robot into a serial slave, controlled by another microcontroller, is given in **Section 10.a** of the **Pololu 3pi Robot User's Guide** [<http://www.pololu.com/docs/0J21>]. This library also comes with an example program in `libpololu-avr/examples`:

### serial1

```
#include <pololu/orangutan.h>

/*
 * serial1: for the Orangutan controllers and 3pi robot.
 *
 * This example listens for bytes on PD0/RXD. Whenever it receives a byte, it
 * performs a custom action. Whenever the user presses the middle button, it
 * transmits a greeting on PD1/TXD.
 *
 * The Baby Orangutan does not have a green LED, LCD, or pushbuttons so
 * that part of the code will not work.
 *
 * To make this example compile for the Orangutan SVP, you
 * must add a first argument of UART0 to all the serial_*
 * function calls.
 *
 * http://www.pololu.com/docs/0J20
 * http://www.pololu.com
 * http://forum.pololu.com
 */

// receive_buffer: A ring buffer that we will use to receive bytes on PD0/RXD.
// The OrangutanSerial library will put received bytes in to
// the buffer starting at the beginning (receiveBuffer[0]).
// After the buffer has been filled, the library will automatically
// start over at the beginning.
char receive_buffer[32];

// receive_buffer_position: This variable will keep track of which bytes in the receive buffer
// we have already processed. It is the offset (0-31) of the next byte
// in the buffer to process.
unsigned char receive_buffer_position = 0;

// send_buffer: A buffer for sending bytes on PD1/TXD.
char send_buffer[32];
```

```

// wait_for_sending_to_finish: Waits for the bytes in the send buffer to
// finish transmitting on PD1/TXD. We must call this before modifying
// send_buffer or trying to send more bytes, because otherwise we could
// corrupt an existing transmission.
void wait_for_sending_to_finish()
{
    while(!serial_send_buffer_empty());
}

// process_received_byte: Responds to a byte that has been received on
// PD0/RXD. If you are writing your own serial program, you can
// replace all the code in this function with your own custom behaviors.
void process_received_byte(char byte)
{
    switch(byte)
    {
        // If the character 'G' is received, turn on the green LED.
        case 'G':
            green_led(1);
            break;

        // If the character 'g' is received, turn off the green LED.
        case 'g':
            green_led(0);
            break;

        // If the character 'c' is received, play the note c.
        case 'c':
            play_from_program_space(PSTR("c16"));
            break;

        // If the character 'd' is received, play the note d.
        case 'd':
            play_from_program_space(PSTR("d16"));
            break;

        // If any other character is received, change its capitalization and
        // send it back.
        default:
            wait_for_sending_to_finish();
            send_buffer[0] = byte ^ 0x20;
            serial_send(send_buffer, 1);
            break;
    }
}

void check_for_new_bytes_received()
{
    while(serial_get_received_bytes() != receive_buffer_position)
    {
        // Process the new byte that has just been received.
        process_received_byte(receive_buffer[receive_buffer_position]);

        // Increment receive_buffer_position, but wrap around when it gets to
        // the end of the buffer.
        if (receive_buffer_position == sizeof(receive_buffer)-1)
        {
            receive_buffer_position = 0;
        }
        else
        {
            receive_buffer_position++;
        }
    }
}

int main()
{
    // Set the baud rate to 9600 bits per second. Each byte takes ten bit
    // times, so you can get at most 960 bytes per second at this speed.
    serial_set_baud_rate(9600);

    // Start receiving bytes in the ring buffer.
    serial_receive_ring(receive_buffer, sizeof(receive_buffer));

    while(1)

```

```

{
    // Deal with any new bytes received.
    check_for_new_bytes_received();

    // If the user presses the middle button, send "Hi there!"
    // and wait until the user releases the button.
    if (button_is_pressed(MIDDLE_BUTTON))
    {
        wait_for_sending_to_finish();
        memcpy_P(send_buffer, PSTR("Hi there!\r\n"), 11);
        serial_send(send_buffer, 11);

        // Wait for the user to release the button. While the processor is
        // waiting, the OrangutanSerial library will take care of receiving
        // bytes using the serial reception interrupt. But if enough bytes
        // arrive during this period to fill up the receive buffer, then the
        // older bytes will be lost and we won't know exactly how many bytes
        // have been received.
        wait_for_button_release(MIDDLE_BUTTON);
    }
}
}

```

## 6.k. Orangutan Servo Control Functions

### Overview

This section of the library provides commands for generating digital pulses to control servos.

Complete documentation of these functions can be found in **Section 10** of the **Pololu AVR Library Command Reference** [<http://www.pololu.com/docs/0J467>].

**Note:** The OrangutanServos and OrangutanBuzzer libraries both use Timer 1, so they **will conflict with each other and any other code that relies on or reconfigures Timer 1.**

### Servos

A servo motor (also called hobby servo or RC servo) is a device containing a motor that you can command to turn to a specific location. To control a servo, you must connect its three wires properly. The **black** wire is ground, and should be connected to the ground line of your Orangutan. The **red** line is power, and should be connected to power supply with a voltage that is within the operating range of your servo, and that is capable of supplying all the current that your servo might draw. The **white** line is signal, and should be connected to a pin that generates servo pulses, such as an I/O line on the Orangutan. The Orangutan I/O header blocks make it easy to connect your servos, because each column of the block contains ground, power, and an I/O line in the correct order.

To make your servo move, you must output a high pulse to the signal line every 20 ms. The pulse width (also called pulse length or pulse duration) determines which position the servo will move to. Thus, every pulse width (typically measured in microseconds) corresponds to some angle (typically measured in degrees) of the servo's output shaft. Typical servos have a limited range of motion, and this entire range of motion can be reached with pulse widths between 1 ms and 2 ms.

Take care when choosing pulse widths, because some servos are capable of breaking themselves if they are commanded to move to a position outside their range of motion. To start off, you can send pulse widths of 1.5 ms and then slowly change the pulse width until you discover its upper and lower limits.

## Orangutan Servo Control

The OrangutanServos section of the library allows you to generate the control pulses for up to 16 servos.

**On every Orangutan except the Orangutan SVP**, each servo requires one free I/O pin. The library allows you to choose which I/O pins to use for your servos. On the **Baby Orangutan B**, there are enough free I/O lines for you to control the full 16 servos. On the **Orangutan SV** and **Orangutan LV-168**, there are 8 free I/O lines so you can easily control eight servos, but you can control more servos if you remove the LCD or other unused hardware. The pulses are generated using software PWM.

**On the Orangutan SVP**, the pulses (for your first 8 servos) are all generated on pin PD5. This pin is a hardware PWM output (OC1A), so the OrangutanServos library generates the servo pulses using hardware PWM, which is more accurate and takes less CPU time than software PWM. Pin PD5 is connected to the input line of an on-board 8-output demultiplexer. If you just need to control one servo, you can leave the demultiplexer input lines disconnected, and plug your servo in to servo port 0. If you want to control more than one servo, then you must choose which free I/O lines to connect to the demultiplexer's three output-selection lines. If you use one I/O line, you can control two servos. If you use two I/O lines, you can control up to four servos. If you use three I/O lines, then you can control up to eight servos. If you need to control more than 8 servos then you can use software PWM to control up to eight more servos (for a total of 16).

## Usage Examples

This library comes with several examples in `libpololu-avr/examples`.

### 1. svp-one-servo

This example program demonstrates how to control one servo on the Orangutan SVP using PD5.

```
#include <pololu/orangutan.h>

/*
 * svp-one-servo: for the Orangutan SVP.
 *
 * This example uses the OrangutanServos functions to control one servo.
 * The servo pulse signal is sent on pin PD5, which is hardwired to the
 * input of the demux. The servo signal is available on demux output 0.
 * This example uses the OrangutanPushbuttons functions to take input
 * from the user, and the OrangutanLCD functions to display feedback on
 * the LCD.
 *
 * http://www.pololu.com/docs/0J20
 * http://www.pololu.com
 * http://forum.pololu.com
 */

int main()
{
    const unsigned char demuxPins[] = {};
    servos_init(demuxPins, sizeof(demuxPins));

    set_servo_target(0, 1300);    // Make the servo go to a neutral position.

    clear(); // Clear the LCD.

    while(1) // Loop forever.
    {
        // When the user presses the top button, execute a pre-programmed
        // sequence of servo movements.
        if (button_is_pressed(TOP_BUTTON))
        {
            // Set the servo speed to 150. This means that the pulse width
            // will change by at most 15 microseconds every 20 ms. So it will
            // take 1.33 seconds to go from a pulse width of 1000 us to 2000 us.
        }
    }
}
```



```

        set_servo_speed(0, 150);

        // Slowly move the servo to position 1800.
        set_servo_target(0, 1800);
        delay_ms(700);

        // Disable the speed limit
        set_servo_speed(0, 0);

        // Make the servo move back to position 1300 as fast as possible.
        set_servo_target(0, 1300);
    }

    if (button_is_pressed(BOTTOM_BUTTON))
    {
        // While the user holds down the bottom button, move the servo
        // slowly towards position 1800.
        set_servo_speed(0, 60);
        set_servo_target(0, 1800);
        wait_for_button_release(BOTTOM_BUTTON);

        // When the user releases the bottom button, print its current
        // position (in microseconds) and then move it back quickly.
        clear();
        print_long(get_servo_position(0));
        print_from_program_space(PSTR(" \xE4s"));
        set_servo_speed(0, 0);
        set_servo_target(0, 1300);
    }
}

// Local Variables: **
// mode: C **
// c-basic-offset: 4 **
// tab-width: 4 **
// indent-tabs-mode: t **
// end: **

```

## 2. svp-eight-servo

This example program demonstrates how to control up to eight servos on the Orangutan SVP using the hardware demultiplexer.

```

#include <pololu/orangutan.h>

/*
 * svp-eight-servo: for the Orangutan SVP.
 *
 * This example uses the OrangutanServos functions to control eight servos.
 * To use this example, you must connect the correct AVR I/O pins to their
 * corresponding servo demultiplexer output-selection pins.
 *   - Connect PB3 to SA.
 *   - Connect PB4 to SB.
 *   - Connect PC0 to SC.
 *
 * http://www.pololu.com/docs/0J20
 * http://www.pololu.com
 * http://forum.pololu.com
 */

int main()
{
    // This array specifies the correspondence between I/O pins and DEMUX
    // output-selection pins. This demo uses three pins, which allows you
    // to control up to 8 servos. You can also use two, one, or zero pins
    // to control fewer servos.
    const unsigned char demuxPins[] = {IO_B3, IO_B4, IO_C0}; // eight servos, B3=SA, B4=SB, C0=B5.
    //const unsigned char demuxPins[] = {IO_B3, IO_B4};       // four servos, B3=SA, B4=SB
    //const unsigned char demuxPins[] = {IO_B3};              // two servos, B3=SA
    //const unsigned char demuxPins[] = {};                    // one servo

    servos_init(demuxPins, sizeof(demuxPins));

    // Set the servo speed to 150. This means that the pulse width

```

```

// will change by at most 15 microseconds every 20 ms. So it will
// take 1.33 seconds to go from a pulse width of 1000 us to 2000 us.
set_servo_speed(0, 150);
set_servo_speed(1, 150);
set_servo_speed(2, 150);
set_servo_speed(3, 150);
set_servo_speed(4, 150);
set_servo_speed(5, 150);
set_servo_speed(6, 150);
set_servo_speed(7, 150);

// Make all the servos go to a neutral position.
set_servo_target(0, 1300);
set_servo_target(1, 1300);
set_servo_target(2, 1300);
set_servo_target(3, 1300);
set_servo_target(4, 1300);
set_servo_target(5, 1300);
set_servo_target(6, 1300);
set_servo_target(7, 1300);

while(1) // Loop forever.
{
    // When the user presses the top button, execute a pre-programmed
    // sequence of servo movements.
    if (button_is_pressed(TOP_BUTTON))
    {
        set_servo_target(0, 1800); delay_ms(350);
        set_servo_target(1, 1800); delay_ms(350);
        set_servo_target(2, 1800); delay_ms(350);
        set_servo_target(3, 1800); delay_ms(350);
        set_servo_target(4, 1800); delay_ms(350);
        set_servo_target(5, 1800); delay_ms(350);
        set_servo_target(6, 1800); delay_ms(350);
        set_servo_target(7, 1800); delay_ms(1000);

        set_servo_target(0, 1300); delay_ms(350);
        set_servo_target(1, 1300); delay_ms(350);
        set_servo_target(2, 1300); delay_ms(350);
        set_servo_target(3, 1300); delay_ms(350);
        set_servo_target(4, 1300); delay_ms(350);
        set_servo_target(5, 1300); delay_ms(350);
        set_servo_target(6, 1300); delay_ms(350);
        set_servo_target(7, 1300); delay_ms(350);
    }
}
}

```

### 3. svp-sixteen-servo

This example program demonstrates how to control up to sixteen servos on the Orangutan SVP using the hardware demultiplexer.

```

#include <pololu/orangutan.h>

/*
 * svp-sixteen-servo: for the Orangutan SVP.
 *
 * This example uses the OrangutanServos functions to control sixteen servos.
 * To use this example, you must connect the correct AVR I/O pins to their
 * corresponding servo demultiplexer output-selection pins.
 *   - Connect PB3 to SA.
 *   - Connect PB4 to SB.
 *   - Connect PC0 to SC.
 * Servos a0-a7 will be on the servo demux outputs.
 * Servos b0-b7 will be on pins PA0-PA7.
 *
 * http://www.pololu.com/docs/0J20
 * http://www.pololu.com
 * http://forum.pololu.com
 */

int main()
{
    // This array specifies the correspondence between I/O pins and DEMUX

```

```

// output-selection pins. This demo uses three pins, which allows you
// to control up to 8 servos from the demux.
const unsigned char demuxPins[] = {IO_B3, IO_B4, IO_C0}; // B3=SA, B4=SB, C0=B5.

// This array specifies the correspondence between I/O pins and
// software-PWMed servos.
const unsigned char servoPinsB[] = {IO_A0, IO_A1, IO_A2, IO_A3, IO_A4, IO_A5, IO_A6, IO_A7};

servos_init_extended(demuxPins, sizeof(demuxPins), servoPinsB, sizeof(servoPinsB));

// Set the servo speed to 150. This means that the pulse width
// will change by at most 15 microseconds every 20 ms. So it will
// take 1.33 seconds to go from a pulse width of 1000 us to 2000 us.
set_servo_speed(0, 150); // Servo a0 = Demux output 0
set_servo_speed(1, 150); // Servo a1 = Demux output 1
set_servo_speed(2, 150); // Servo a2 = Demux output 2
set_servo_speed(3, 150); // Servo a3 = Demux output 3
set_servo_speed(4, 150); // Servo a4 = Demux output 4
set_servo_speed(5, 150); // Servo a5 = Demux output 5
set_servo_speed(6, 150); // Servo a6 = Demux output 6
set_servo_speed(7, 150); // Servo a7 = Demux output 7
set_servo_speedB(0, 150); // Servo b0 = pin A0
set_servo_speedB(1, 150); // Servo b1 = pin A1
set_servo_speedB(2, 150); // Servo b2 = pin A2
set_servo_speedB(3, 150); // Servo b3 = pin A3
set_servo_speedB(4, 150); // Servo b4 = pin A4
set_servo_speedB(5, 150); // Servo b5 = pin A5
set_servo_speedB(6, 150); // Servo b6 = pin A6
set_servo_speedB(7, 150); // Servo b7 = pin A7

// Make all the servos go to a neutral position.
set_servo_target(0, 1300);
set_servo_target(1, 1300);
set_servo_target(2, 1300);
set_servo_target(3, 1300);
set_servo_target(4, 1300);
set_servo_target(5, 1300);
set_servo_target(6, 1300);
set_servo_target(7, 1300);
set_servo_targetB(0, 1300);
set_servo_targetB(1, 1300);
set_servo_targetB(2, 1300);
set_servo_targetB(3, 1300);
set_servo_targetB(4, 1300);
set_servo_targetB(5, 1300);
set_servo_targetB(6, 1300);
set_servo_targetB(7, 1300);

while(1) // Loop forever.
{
    // When the user presses the top button, execute a pre-programmed
    // sequence of servo movements.
    if (button_is_pressed(TOP_BUTTON))
    {
        set_servo_target(0, 1800); delay_ms(350);
        set_servo_target(1, 1800); delay_ms(350);
        set_servo_target(2, 1800); delay_ms(350);
        set_servo_target(3, 1800); delay_ms(350);
        set_servo_target(4, 1800); delay_ms(350);
        set_servo_target(5, 1800); delay_ms(350);
        set_servo_target(6, 1800); delay_ms(350);
        set_servo_target(7, 1800); delay_ms(350);
        set_servo_targetB(0, 1800); delay_ms(350);
        set_servo_targetB(1, 1800); delay_ms(350);
        set_servo_targetB(2, 1800); delay_ms(350);
        set_servo_targetB(3, 1800); delay_ms(350);
        set_servo_targetB(4, 1800); delay_ms(350);
        set_servo_targetB(5, 1800); delay_ms(350);
        set_servo_targetB(6, 1800); delay_ms(350);
        set_servo_targetB(7, 1800); delay_ms(1000);

        set_servo_target(0, 1300); delay_ms(350);
        set_servo_target(1, 1300); delay_ms(350);
        set_servo_target(2, 1300); delay_ms(350);
        set_servo_target(3, 1300); delay_ms(350);
        set_servo_target(4, 1300); delay_ms(350);
        set_servo_target(5, 1300); delay_ms(350);
    }
}

```

```

        set_servo_target(6, 1300); delay_ms(350);
        set_servo_target(7, 1300); delay_ms(350);
        set_servo_targetB(0, 1300); delay_ms(350);
        set_servo_targetB(1, 1300); delay_ms(350);
        set_servo_targetB(2, 1300); delay_ms(350);
        set_servo_targetB(3, 1300); delay_ms(350);
        set_servo_targetB(4, 1300); delay_ms(350);
        set_servo_targetB(5, 1300); delay_ms(350);
        set_servo_targetB(6, 1300); delay_ms(350);
        set_servo_targetB(7, 1300); delay_ms(350);
    }
}

// Local Variables: **
// mode: C **
// c-basic-offset: 4 **
// tab-width: 4 **
// indent-tabs-mode: t **
// end: **

```

## 6.1. Orangutan SVP Functions

### Overview

The **Orangutan SVP** [<http://www.pololu.com/catalog/product/1325>] is based on the AVR ATmega324 or ATmega1284 processor. It has an auxiliary processor that provides the USB connection, five configurable input lines, and battery voltage reading. Several parts of the Pololu AVR C/C++ Library have built-in support for using the auxiliary processor, so you will not need to worry about the details of the Serial Peripheral Interface (SPI) protocol used to talk to the auxiliary processor. If you are curious about the details of the SPI protocol, you can read the C++ source code of the library.

Complete documentation of the SVP-specific functions can be found in **Section 12** of the **Pololu AVR Library Command Reference** [<http://www.pololu.com/docs/0J18>].

An overview of the analog input functions, which support reading the analog inputs on the SVP's auxiliary processor, can be found in **Section 6.c**. An overview of the serial port communication functions, which support sending and receiving bytes from the computer via the auxiliary processor's USB connection, can be found in **Section 6.j**.

### Setting the mode

One of the first things to think about when writing a program for the SVP is what mode you want the auxiliary processor to be in.

If you want to use quadrature encoders, you can use the **SVP\_MODE\_ENCODERS** mode and let the auxiliary processor handle the readings from two quadrature encoders on lines A, B, C and D/RX.

If you want to maximize the number of analog inputs available, you can use the **SVP\_MODE\_ANALOG** mode which makes A, B, C, and D/RX be analog inputs. The ADC/SS line is also available as an analog input. It is hardwired to a user trimpot, but you can cut the labeled trace between ADC/SS and POT on the bottom of the board to disconnect the pot, and then connect something else to that pin. This allows you to use a total of 13 analog inputs: eight on the AVR and five on the auxiliary processor. All 13 inputs can be read using the same functions (see **Section 6.c**), so you don't need to worry too much about which processor is converting them.

If you want to receive TTL-level serial bytes on your computer, you can use the **SVP\_MODE\_RX** mode (the default) which makes A, B, and C be analog inputs and D/RX be the serial receive line. In this mode, TTL-level serial bytes received on the RX line will be sent to the computer

on the Pololu Orangutan SVP TTL Serial Port. The RX line, along with the TX line (which is always the serial transmit line) make the Orangutan SVP's auxiliary processor function as a USB-to-TTL-serial adapter for your computer, allowing you to control serial devices from your computer. Alternatively, you can control the serial devices directly from the AVR using the functions in **Section 6.j** and you can use the RX line to monitor and debug the bytes that are being transmitted (or received) by the AVR.

You can use the **setMode()** command at the beginning of your program to set the mode of the auxiliary processor. See the Pololu AVR Library Command Reference for details.

## Powered by SPI

Whenever you call a function in the Pololu AVR Library that uses the auxiliary processor, the function might initiate SPI communication to the auxiliary processor. This means that the MOSI (PB5) and SCK (PB7) pins will be set to outputs, the MISO (PB6) pin will be set as an input, a pull-up resistor will be enabled on SS (PB4) if it is an input, and the AVR's hardware SPI module will be enabled. The functions that do this include any analog input function that uses an input on the auxiliary processor, any function for reading the battery voltage or trimpot, any serial port function that uses the **USB COMM** port, and any function specific to the Orangutan SVP (**Section 12** of the Command Reference).

## PB4 should be an output

In order for the functions that talk to the auxiliary processor to work, the **SS (PB4) pin must either be an output or be an input that is always high**. The AVR's SPI module is designed so that if SS is an input and it reads low (0 V), then the SPI module will automatically go in to slave mode (the MSTR bit in SPCR will become zero), making it impossible to communicate with the auxiliary processor. Therefore, it is recommended that you make SS an output at the beginning of your program. This can be done with one of the following lines of code:

```
set_digital_output(IO_B4, LOW); // Make SSbar an output (C only)

OrangutanDigital::setOutput(IO_B4, LOW); // Make SSbar an output (C++ only)

DDRB |= 1<<DDB4; // Make SSbar an output
```

## Usage Examples

This library comes with an example program in `libpololu-avr/examples`.

### 1. svp1

A simple example that demonstrates some SVP-specific functions.

```
#include <pololu/orangutan.h>

/*
 * svp1: for the Orangutan SVP.
 *
 * This example uses the OrangutanSVP functions to set the mode of the
 * auxiliary processor, take analog readings on line D/RX, and display
 * information about the Orangutan's current USB device state on the LCD.
 *
 * http://www.pololu.com/docs/0J20
 * http://www.pololu.com
 * http://forum.pololu.com
 */

int main()
{
    // Make SSbar be an output so it does not interfere with SPI communication.
```

```

set_digital_output(IO_B4, LOW);

// Set the mode to SVP_MODE_ANALOG so we can get analog readings on line D/RX.
svp_set_mode(SVP_MODE_ANALOG);

while(1)
{
    clear(); // Erase the LCD.

    if (usb_configured())
    {
        // Connected to USB and the computer recognizes the device.
        print("USB");
    }
    else if (usb_power_present())
    {
        // Connected to USB.
        print("usb");
    }

    if (usb_suspend())
    {
        // Connected to USB, in the Suspend state.
        lcd_goto_xy(4,0);
        print("SUS");
    }

    if (dtr_enabled())
    {
        // The DTR virtual handshaking line is 1.
        // This often means that a terminal program is connected to the
        // Pololu Orangutan SVP USB Communication Port.
        lcd_goto_xy(8,0);
        print("DTR");
    }

    if (rts_enabled())
    {
        // The RTS virtual handshaking line is 1.
        lcd_goto_xy(12,0);
        print("RTS");
    }

    // Display an analog reading from channel D, in millivolts.
    lcd_goto_xy(0,1);
    print("Channel D: ");
    print_long(analog_read_millivolts(CHANNEL_D));

    // Wait for 100 ms, otherwise the LCD would flicker.
    delay_ms(100);
}
}

```

## 6.m. Pololu QTR Sensor Functions

### Overview

This set of functions provides access to the QTR family of reflectance sensors, which come as single-sensor units (**QTR-1A** [<http://www.pololu.com/catalog/product/958>] and **QTR-1RC** [<http://www.pololu.com/catalog/product/959>]) or as 8-sensor arrays (**QTR-8A** [<http://www.pololu.com/catalog/product/960>] and **QTR-8RC** [<http://www.pololu.com/catalog/product/961>]). To initialize the set of sensors that you are using, choose either the **qtr\_analog\_init()** or **qtr\_rc\_init()** function, and specify the set of pins connected to the sensors that you will be using. The initialization may only be called once within the C environment, while C++ allows the sensors to be used in more complicated ways.

These functions are used by the 3pi support described in the **3pi Robot User's Guide** [<http://www.pololu.com/docs/0J21>]. We do not recommend using these functions directly on the 3pi unless you are adding additional sensors.

C++ users: See **Section 3 of Programming Orangutans and the 3pi Robot from the Arduino Environment** [<http://www.pololu.com/docs/0J19>] for examples of this class in the Arduino environment, which is almost identical to C++.

Complete documentation of these functions can be found in **Section 14 of the Pololu AVR Library Command Reference** [<http://www.pololu.com/docs/0J18>].

## Usage Notes

### Calibration

This library allows you to use the **calibrate()** method to easily calibrate your sensors for the particular conditions it will encounter. Calibrating your sensors can lead to substantially more reliable sensor readings, which in turn can help simplify your code since. As such, we recommend you build a calibration phase into your application's initialization routine. This can be as simple as a fixed duration over which you repeated call the **calibrate()** method. During this calibration phase, you will need to expose each of your reflectance sensors to the lightest and darkest readings they will encounter. For example, if you have made a line follower, you will want to slide it across the line during the calibration phase so the each sensor can get a reading of how dark the line is and how light the ground is. A sample calibration routine would be:

```
#include <pololu/orangutan.h>

int main()
{
    // initialize your QTR sensors
    unsigned char qtr_rc_pins[] = {14, 15, 16};
    qtr_rc_init(qtr_rc_pins, 3, 2000, 255); // 800 us timeout, no emitter pin
    // int qtr_analog_pins[] = {0, 1, 2};
    // qtr_analog_init(qtr_analog_pins, 3, 10, 14); // 10 samples, emitter pin is PC0

    // optional: wait for some input from the user, such as a button press

    // then start calibration phase and move the sensors over both
    // reflectance extremes they will encounter in your application:
    int i;
    for (i = 0; i < 250; i++) // make the calibration take about 5 seconds
    {
        qtr_calibrate(QTR_EMITTERS_ON);
        delay(20);
    }

    // optional: signal that the calibration phase is now over and wait for further
    // input from the user, such as a button press

    while (1)
    {
        // main body of program goes here
    }

    return 0;
}
```

### Reading the Sensors

This library gives you a number of different ways to read the sensors.

1. You can request raw sensor values using the **read()** method, which takes an optional argument that lets you perform the read with the IR emitters turned off (note that turning the emitters off is only supported by the QTR-8x reflectance sensor arrays).
2. You can request calibrated sensor values using the **qtr\_read\_calibrated()** function, which also takes an optional argument that lets you perform the read with the IR emitters turned off. Calibrated sensor values will always range from 0 to 1000, with 0 being as or more reflective (i.e. whiter) than the most reflective surface encountered during calibration,

and 1000 being as or less reflective (i.e. blacker) than the least reflective surface encountered during calibration.

3. For line-detection applications, you can request the line location using the **qtr\_read\_line()** functions, which takes as optional parameters a boolean that indicates whether the line is white on a black background or black on a white background, and a boolean that indicates whether the IR emitters should be on or off during the measurement. **qtr\_read\_line()** provides calibrated values for each sensor and returns an integer that tells you where it thinks the line is. If you are using  $N$  sensors, a returned value of 0 means it thinks the line is on or to the outside of sensor 0, and a returned value of  $1000 * (N-1)$  means it thinks the line is on or to the outside of sensor  $N-1$ . As you slide your sensors across the line, the line position will change monotonically from 0 to  $1000 * (N-1)$ , or vice versa. This line-position value can be used for closed-loop PID control.

A sample routine to obtain the sensor values and perform rudimentary line following would be:

```
void loop() // call this routine repeatedly from your main program
{
    unsigned int sensors[3];
    // get calibrated sensor values returned in the sensors array, along with the line position
    // position will range from 0 to 2000, with 1000 corresponding to the line over the middle sensor
    int position = qtr_read_line(sensors, QTR_EMITTERS_ON);

    // if all three sensors see very low reflectance, take some appropriate action for this situation
    if (sensors[0] > 750 && sensors[1] > 750 && sensors[2] > 750)
    {
        // do something. Maybe this means we're at the edge of a course or about to fall off a table,
        // in which case, we might want to stop moving, back up, and turn around.
        return;
    }

    // compute our "error" from the line position. We will make it so that the error is zero when
    // the middle sensor is over the line, because this is our goal. Error will range from
    // -1000 to +1000. If we have sensor 0 on the left and sensor 2 on the right, a reading of -1000
    // means that we see the line on the left and a reading of +1000 means we see the line on
    // the right.
    int error = position - 1000;

    int leftMotorSpeed = 100;
    int rightMotorSpeed = 100;
    if (error < -500) // the line is on the left
        leftMotorSpeed = 0; // turn left
    if (error > 500) // the line is on the right
        rightMotorSpeed = 0; // turn right

    // set motor speeds using the two motor speed variables above
}
```

## PID Control

The integer value returned by **qtr\_read\_line()** can be easily converted into a measure of your position error for line-following applications, as was demonstrated in the previous code sample. The function used to generate this position/error value is designed to be monotonic, which means the value will almost always change in the same direction as you sweep your sensors across the line. This makes it a great quantity to use for PID control.

Explaining the nature of PID control is beyond the scope of this document, but Wikipedia has a very good **article** [[http://en.wikipedia.org/wiki/PID\\_controller](http://en.wikipedia.org/wiki/PID_controller)] on the subject.

The following code gives a very simple example of PD control (I find the integral PID term is usually not necessary when it comes to line following). The specific nature of the constants will be determined by your particular application, but you should note that the derivative constant  $K_d$  is usually much bigger than the proportional constant  $K_p$ . This is because the derivative of



the error is a much smaller quantity than the error itself, so in order to produce a meaningful correction it needs to be multiplied by a much larger constant.

```
int lastError = 0;

void loop() // call this routine repeatedly from your main program
{
    unsigned int sensors[3];
    // get calibrated sensor values returned in the sensors array, along with the line position
    // position will range from 0 to 2000, with 1000 corresponding to the line over the middle sensor
    int position = qtr_read_line(sensors, QTR_EMITTERS_ON);

    // compute our "error" from the line position. We will make it so that the error is zero when
    // the middle sensor is over the line, because this is our goal. Error will range from
    // -1000 to +1000. If we have sensor 0 on the left and sensor 2 on the right, a reading of -1000
    // means that we see the line on the left and a reading of +1000 means we see the line on
    // the right.
    int error = position - 1000;

    // set the motor speed based on proportional and derivative PID terms
    // KP is the a floating-point proportional constant (maybe start with a value around 0.1)
    // KD is the floating-point derivative constant (maybe start with a value around 5)
    // note that when doing PID, it's very important you get your signs right, or else the
    // control loop will be unstable
    int motorSpeed = KP * error + KD * (error - lastError);
    lastError = error;

    // M1 and M2 are base motor speeds. That is to say, they are the speeds the motors should
    // spin at if you are perfectly on the line with no error. If your motors are well matched,
    // M1 and M2 will be equal. When you start testing your PID loop, it might help to start with
    // small values for M1 and M2. You can then increase the speed as you fine-tune your
    // PID constants KP and KD.
    int m1Speed = M1 + motorSpeed;
    int m2Speed = M2 - motorSpeed;

    // it might help to keep the speeds positive (this is optional)
    // note that you might want to add a similar line to keep the speeds from exceeding
    // any maximum allowed value
    if (m1Speed < 0)
        m1Speed = 0;
    if (m2Speed < 0)
        m2Speed = 0;

    // set motor speeds using the two motor speed variables above
}
```

## 6.n. Pololu Wheel Encoder functions

The PololuWheelEncoders class and the associated C functions provide an easy interface for using the **Pololu Wheel Encoders** [<http://www.pololu.com/catalog/product/1217>], which allow a robot to know exactly how far its motors have turned at any point in time. Note that this library should work with all standard quadrature encoders, not just the Pololu Wheel Encoders.

This section of the library makes uses of pin-change interrupts to quickly detect and record each transition on the encoder. Interrupt vectors for PCINT0, PCINT1, PCINT2 will be defined if functions from this library are used, even if the pins selected are all on a single port, so **this section of the library will conflict with any other uses of these interrupts**. The interrupt service routine (ISR) will take about 20-30 us. If you need better control of the interrupts used, or you want to write a more efficient ISR, you can copy the library code from PololuWheelEncoders.cpp into your own project and modify it as necessary.

Complete documentation of this library's methods can be found in **Section 16** of the **Pololu AVR Library Command Reference** [<http://www.pololu.com/docs/0J18>].

## Usage Notes

The two sensors A and B on the encoder board go through a four-step cycle as each tooth of the wheel passes by, for a total of 48 counts per revolution. This corresponds to about 3 mm for each count, though you will have to calibrate values for your own robot to get a precise measure of distance.

Normally, there will be at least 1 ms between counts, which gives the ISR plenty of time to finish one count before the next one occurs. This is very important, because if two counts occur quickly enough, the ISR will not be able to determine the direction of rotation. In this case, an error can be detected by the functions **encoders\_check\_error\_m1()** or **encoders\_check\_error\_m2()**. An error like this either corresponds to a miscalibration of the encoder or a timing issue with the software. For example, if interrupts are disabled for several ms while the wheels are spinning quickly, errors will probably occur.

## Usage Examples

This library comes with one example program in `libpololu-avr/examples`. The example measures the outputs of two encoders, one connected to ports PC2 and PC3, and another connected to ports PC4 and PC5 – these are the leftmost four ports on the Orangutan. The values of the two encoder outputs are displayed on the LCD, and errors (if any) are reported below. For use on the Baby Orangutan, remove the LCD display code (and come up with some other way to use the values).

### 1. wheel\_encoders1

```
#include <pololu/orangutan.h>
#include <avr/interrupt.h>

int main()
{
    encoders_init(16,17,18,19); // the Arduino numbers for ports PC2 - PC5

    while(1)
    {
        lcd_goto_xy(0,0);
        print_long(encoders_get_counts_m1());
        print(" ");

        lcd_goto_xy(4,0);
        print_long(encoders_get_counts_m2());
        print(" ");

        if(encoders_check_error_m1())
        {
            lcd_goto_xy(0,1);
            print("Error 1");
        }
        if(encoders_check_error_m2())
        {
            lcd_goto_xy(0,1);
            print("Error 2");
        }

        delay_ms(50);
    }
}
```

## 7. Using the Pololu AVR Library for your own projects

After getting one of the simple examples to work with an Orangutan controller or 3pi robot, you can start working on more complicated programs of your own. The library provides easy access to all of the features of the Orangutans and 3pi, including the LCD screen, buttons, LEDs, motors, and buzzer. There are also functions in the library that make it easy for you to do more general-purpose operations with the AVR, such as timing and analog-to-digital conversion. The library also provides support for the **Pololu QTR sensors** [<http://www.pololu.com/catalog/product/961>] and the **Pololu Wheel Encoders** [<http://www.pololu.com/catalog/product/1217>] (it should actually work for quadrature encoders in general). For a complete list of functions provided by the library, see the **command reference** [<http://www.pololu.com/docs/0J18>].

Usually, the easiest way to adapt this code to your own projects will be to start with a working example and gradually add the things that you need, one step at a time. However, if you want to start from scratch, there are just a few things that you need to know. First, to use the library with C, you must place one of the following lines

```
#include <pololu/orangutan.h>
#include <pololu/3pi.h>
#include <pololu/qtr.h>
#include <pololu/encoders.h>
```


at the top of any C file that uses functions provided by the library. To use the library with C++, the equivalent lines are

```
#include <pololu/orangutan>
#include <pololu/Pololu3pi.h>
#include <pololu/PololuQTRSensors.h>
```

The line or lines that you include depend on which product you are using with the library.

Second, when compiling, you must link your object files with the appropriate `libpololu_atmegaX.a` file. This is accomplished by passing the `-lpololu_atmegaX` option to `avr-gcc` during the linking step, where `X` can be 48, 168, 328p, 324p or 1284p.

To add the `-lpololu_atmegaX` option within AVR studio, select **Project > Configuration Options > Libraries**. You should see `libpololu_atmega48.a`, `libpololu_atmega168.a`, `libpololu_atmega328p.a`, `libpololu_atmega324p.a`, and `libpololu_atmega1284p.a` listed as options in the left column. Select the file that matches the microcontroller you are programming and click “add library” to add it to your project. Note that the 3pi robots with serial numbers less than **0J5840** use the ATmega168 microcontroller; 3pi robots with serial number 0J5840 or greater use the ATmega328 microcontroller.




**AVR Studio library settings for using the Pololu AVR library (libpololu).**

Finally, we also strongly recommend the linker option `-wl,-gc-sections`. This causes unused library functions to not be included, resulting in a much smaller code size. To include this in AVR Studio, select **Project > Configuration Options > Custom Options**. Click on [Linker options] and add:

`-wl,-gc-sections`

to the list. This linker option is included in both the AVR Studio and Linux-based example programs described earlier.



**Recommended AVR Studio linker options for projects using the Pololu AVR Library.**

## 8. Additional resources

To learn more about programming AVR's and using the Pololu AVR Library, see the following list of resources:

- **Pololu AVR Library Command Reference** [<http://www.pololu.com/docs/0J18>]: detailed information about every function in the library.
- **Programming Orangutans and the 3pi Robot from the Arduino Environment** [<http://www.pololu.com/docs/0J17>]: information about using this library to program Orangutans and the 3pi robot from within the Arduino environment.
- **Arduino Library for the Pololu QTR Reflectance Sensors** [<http://www.pololu.com/docs/0J19>]: information about using the QTR sensor portion of this library from within the Arduino environment.
- **Pololu 3pi Robot User's Guide** [<http://www.pololu.com/docs/0J21>]
- **Pololu Orangutan SV and LV-168 User's Guide** [<http://www.pololu.com/docs/0J27>]
- **Pololu Orangutan SVP User's Guide** [<http://www.pololu.com/docs/0J39>]
- **Pololu Baby Orangutan B User's Guide** [<http://www.pololu.com/docs/0J14>]
- **Pololu USB AVR Programmer User's Guide** [<http://www.pololu.com/docs/0J36>]
- **Pololu Orangutan USB Programmer User's Guide** [<http://www.pololu.com/docs/0J6>]
- **WinAVR** [<http://winavr.sourceforge.net/>]
- **AVR Studio** [<http://www.atmel.com/avrstudio/>]
- **AVR Libc Home Page** [<http://www.nongnu.org/avr-libc/>]
- **ATmega328P** **documentation** [[http://www.atmel.com/dyn/products/product\\_card.asp?PN=ATmega328P](http://www.atmel.com/dyn/products/product_card.asp?PN=ATmega328P)]
- **ATmega324PA** **documentation** [[http://www.atmel.com/dyn/products/product\\_card.asp?PN=ATmega324PA](http://www.atmel.com/dyn/products/product_card.asp?PN=ATmega324PA)]
- **ATmega1284P** **documentation** [[http://www.atmel.com/dyn/products/product\\_card.asp?PN=ATmega1284P](http://www.atmel.com/dyn/products/product_card.asp?PN=ATmega1284P)]
- **ATmega168** **documentation** [[http://www.atmel.com/dyn/products/product\\_card.asp?PN=ATmega168](http://www.atmel.com/dyn/products/product_card.asp?PN=ATmega168)]
- **Tutorial: AVR Programming on the Mac** [<http://bot-thoughts.blogspot.com/2008/02/avr-programming-on-mac.html>]

Finally, we would like to hear your comments and questions over at the **Pololu Robotics Forum** [<http://forum.pololu.com/>]!